globus gass copy

8.6

Generated by Doxygen 1.7.5

Tue Aug 28 2012 20:42:16

Contents

1 Main Page **2**

2 Data Structure Index **2**

2.1 Data Structures . . . 2

3 File Index **2**

3.1 File List . . . 2

4 Data Structure Documentation **3**

4.1 globus_gass_copy_glob_stat_t Struct Reference . . . 3

4.1.1 Detailed Description . . . 3

4.1.2 Field Documentation . . . 3

4.2 globus_gass_copy_state_s Struct Reference . . . 3

4.2.1 Detailed Description . . . 4

4.2.2 Field Documentation . . . 4

4.3 globus_i_gass_copy_buffer_t Struct Reference . . . 4

4.3.1 Detailed Description . . . 4

4.4 globus_i_gass_copy_cancel_s Struct Reference . . . 4

4.4.1 Detailed Description . . . 4

4.5 globus_i_gass_copy_monitor_t Struct Reference . . . 4

4.5.1 Detailed Description . . . 4

4.6 globus_i_gass_copy_state_target_s Struct Reference . . . 5

4.6.1 Detailed Description . . . 5

4.6.2 Field Documentation . . . 5

5 File Documentation **6**

5.1 globus_gass_copy.c File Reference . . . 6

5.1.1 Detailed Description . . . 7

5.1.2 Function Documentation . . . 8

5.2 globus_gass_copy.h File Reference . . . 19

5.2.1 Detailed Description . . . 20

5.2.2 Define Documentation . . . 20

5.2.3 Typedef Documentation . . . 20

5.2.4 Enumeration Type Documentation . . . 21

5.2.5 Function Documentation . . . 21

1 Main Page

The Globus GASS Copy library is motivated by the desire to provide a uniform interface to transfer files specified by different protocols. The goals in doing this are to:

- Provide a robust way to describe and apply file transfer properties for a variety of protocols. These include the standard HTTP, FTP and GSIFTP options. Some of the new file transfer capabilities in GSIFTP are parallel, striping, authentication and TCP buffer sizing.
- Provide a service to support nonblocking file transfer and handle asynchronous file and network events.
- Provide a simple and portable way to implement file transfers.

Any program that uses Globus GASS Copy functions must include "globus_gass_copy.h".

2 Data Structure Index

2.1 Data Structures

Here are the data structures with brief descriptions:

globus_gass_copy_glob_stat_t
Glob expanded entry information **3**

globus_gass_copy_state_s
The state structure contains all that is required to perform a file transfer from a source to a destination **3**

globus_i_gass_copy_buffer_t
The buffer structure used for read/write queue entries **4**

globus_i_gass_copy_cancel_s
Gass copy cancel struct **4**

globus_i_gass_copy_monitor_t
The state monitor struct **4**

globus_i_gass_copy_state_target_s
GASS copy target (e.g **5**

3 File Index

3.1 File List

Here is a list of all documented files with brief descriptions:

globus_gass_copy.c
Globus GASS Copy library **6**

globus_gass_copy.h
Header file for the gass copy library **19**

4 Data Structure Documentation

4.1 globus_gass_copy_glob_stat_t Struct Reference

Data Fields

- **globus_gass_copy_glob_entry_t type**
- char * **unique_id**
- char * **symlink_target**
- int **mode**
- int **mdtm**
- globus_off_t **size**

4.1.1 Detailed Description

Glob expanded entry information.

4.1.2 Field Documentation

4.1.2.1 globus_gass_copy_glob_entry_t globus_gass_copy_glob_stat_t::type

The file type of the entry.

4.1.2.2 char* globus_gass_copy_glob_stat_t::unique_id

A string that uniquely identifies the data that the entry refers to.

A file and a symlink to that file will have the same unique_id. It is NULL for when not available.

4.1.2.3 char* globus_gass_copy_glob_stat_t::symlink_target

This points to the full path of the target of a symlink.

It is NULL for non-symlinks or when not available.

4.1.2.4 int globus_gass_copy_glob_stat_t::mode

An integer specifying the mode of the file.

It is set to -1 when not available.

4.1.2.5 int globus_gass_copy_glob_stat_t::mdtm

An integer specifying the modification time of the file.

It is set to -1 when not available.

4.1.2.6 globus_off_t globus_gass_copy_glob_stat_t::size

A globus_off_t specifying the size of the file.

It is set to -1 when not available.

4.2 globus_gass_copy_state_s Struct Reference

Data Fields

- **globus_i_gass_copy_target_t source**
- **globus_i_gass_copy_target_t dest**
- **globus_i_gass_copy_monitor_t monitor**
- globus_mutex_t **mutex**
- globus_i_gass_copy_cancel_status_t **cancel**

4.2.1 Detailed Description

The state structure contains all that is required to perform a file transfer from a source to a destination.

4.2.2 Field Documentation

4.2.2.1 globus_i_gass_copy_target_t globus_gass_copy_state_s::source

Source information for the file transfer.

4.2.2.2 globus_i_gass_copy_target_t globus_gass_copy_state_s::dest

Dest information for the file transfer.

4.2.2.3 globus_i_gass_copy_monitor_t globus_gass_copy_state_s::monitor

Used for signalling from the various callback functions.

4.2.2.4 globus_mutex_t globus_gass_copy_state_s::mutex

coordinates the modifying of the state, aside from the target structures

4.2.2.5 globus_i_gass_copy_cancel_status_t globus_gass_copy_state_s::cancel

indicates the status of the cancel operation.

4.3 globus_i_gass_copy_buffer_t Struct Reference

4.3.1 Detailed Description

The buffer structure used for read/write queue entries.

4.4 globus_i_gass_copy_cancel_s Struct Reference

4.4.1 Detailed Description

gass copy cancel struct

4.5 globus_i_gass_copy_monitor_t Struct Reference

4.5.1 Detailed Description

The state monitor struct.

4.6 globus_i_gass_copy_state_target_s Struct Reference

Data Fields

- char * **url**
- globus_gass_copy_attr_t * **attr**
- globus_mutex_t **mutex**
- globus_fifo_t **queue**
- int **n_pending**
- int **n_simultaneous**
- int **n_complete**
- globus_i_gass_copy_target_status_t **status**
- globus_gass_copy_url_mode_t **mode**
- union {
  struct {
  } **ftp**
  struct {
  globus_gass_transfer_request_t **request**
  } **gass**
  struct {
  globus_bool_t **free_handle**
  globus_bool_t **seekable**
  } **io**
  } **data**

4.6.1 Detailed Description

GASS copy target (e.g.

source, destination) transfer information.

4.6.2 Field Documentation

4.6.2.1 char* globus_i_gass_copy_state_target_s::url

url for file transfer

4.6.2.2 globus_gass_copy_attr_t* globus_i_gass_copy_state_target_s::attr

attributes to control file transfer

4.6.2.3 globus_mutex_t globus_i_gass_copy_state_target_s::mutex

coordinates the modifying of the target structure

4.6.2.4 globus_fifo_t globus_i_gass_copy_state_target_s::queue

a queue to manage the reading/writing of data buffers

4.6.2.5 int globus_i_gass_copy_state_target_s::n_pending

Used for keeping track of reads/writes in the read/write queue.

4.6.2.6 int globus_i_gass_copy_state_target_s::n_simultaneous

Used to limit the number of n_pending.

4.6.2.7 int globus_i_gass_copy_state_target_s::n_complete

Used to compute the offset for ftp writes.

4.6.2.8 globus_i_gass_copy_target_status_t globus_i_gass_copy_state_target_s::status

signifies the target has been successfully setup

4.6.2.9 globus_gass_copy_url_mode_t globus_i_gass_copy_state_target_s::mode

mode used to identify the below target union struct.

4.6.2.10 struct { ... } globus_i_gass_copy_state_target_s::ftp

ftp specific data

4.6.2.11 globus_gass_transfer_request_t globus_i_gass_copy_state_target_s::request

GASS equivelent of a handle.

4.6.2.12 struct { ... } globus_i_gass_copy_state_target_s::gass

GASS specific data.

4.6.2.13 globus_bool_t globus_i_gass_copy_state_target_s::free_handle

If the IO handle was passed as an argument then FALSE If the IO handle was created internally then TRUE.

4.6.2.14 globus_bool_t globus_i_gass_copy_state_target_s::seekable

Can globus_io_file_seek() be performed on this handle?

4.6.2.15 struct { ... } globus_i_gass_copy_state_target_s::io

IO specific data.

4.6.2.16 union { ... } globus_i_gass_copy_state_target_s::data

data required to perform each type of transfer

5 File Documentation

5.1 globus_gass_copy.c File Reference

Functions

- globus_result_t **globus_gass_copy_handle_init** (globus_gass_copy_handle_t *handle, globus_gass_copy_handleattr_t *attr)
- globus_result_t **globus_gass_copy_handle_destroy** (globus_gass_copy_handle_t *handle)
- globus_result_t **globus_gass_copy_set_buffer_length** (globus_gass_copy_handle_t *handle, int length)
- globus_result_t **globus_gass_copy_get_buffer_length** (globus_gass_copy_handle_t *handle, int *length)
- globus_result_t **globus_gass_copy_set_no_third_party_transfers** (globus_gass_copy_handle_t *handle, globus_bool_t no_third_party_transfers)

- globus_result_t **globus_gass_copy_get_no_third_party_transfers** (globus_gass_copy_handle_t ∗handle, globus_bool_t ∗no_third_party_transfers)
- globus_result_t **globus_gass_copy_set_allocate** (globus_gass_copy_handle_t ∗handle, globus_bool_t send_allo)
- globus_result_t **globus_gass_copy_set_stat_on_expand** (globus_gass_copy_handle_t ∗handle, globus_bool_t always_stat)
- globus_result_t **globus_gass_copy_set_partial_offsets** (globus_gass_copy_handle_t ∗handle, globus_off_t offset, globus_off_t end_offset)
- globus_result_t **globus_gass_copy_get_partial_offsets** (globus_gass_copy_handle_t ∗handle, globus_off_t ∗offset, globus_off_t ∗end_offset)
- globus_result_t **globus_gass_copy_attr_init** (globus_gass_copy_attr_t ∗attr)
- globus_result_t **globus_gass_copy_attr_set_ftp** (globus_gass_copy_attr_t ∗attr, globus_ftp_client_operationattr_t ∗ftp_attr)
- globus_result_t **globus_gass_copy_attr_set_io** (globus_gass_copy_attr_t ∗attr, globus_io_attr_t ∗io_attr)
- globus_result_t **globus_gass_copy_attr_set_gass** (globus_gass_copy_attr_t ∗attr, globus_gass_transfer_requestattr_t ∗gass_attr)
- globus_result_t **globus_gass_copy_get_url_mode** (char ∗url, globus_gass_copy_url_mode_t ∗mode)
- globus_result_t **globus_gass_copy_register_performance_cb** (globus_gass_copy_handle_t ∗handle, **globus_gass_copy_performance_cb_t** callback, void ∗user_arg)
- globus_result_t **globus_gass_copy_get_status** (globus_gass_copy_handle_t ∗handle, globus_gass_copy_status_t ∗status)
- const char ∗ **globus_gass_copy_get_status_string** (globus_gass_copy_handle_t ∗handle)
- globus_result_t **globus_gass_copy_url_to_url** (globus_gass_copy_handle_t ∗handle, char ∗source_url, globus_gass_copy_attr_t ∗source_attr, char ∗dest_url, globus_gass_copy_attr_t ∗dest_attr)
- globus_result_t **globus_gass_copy_url_to_handle** (globus_gass_copy_handle_t ∗handle, char ∗source_url, globus_gass_copy_attr_t ∗source_attr, globus_io_handle_t ∗dest_handle)
- globus_result_t **globus_gass_copy_handle_to_url** (globus_gass_copy_handle_t ∗handle, globus_io_handle_t ∗source_handle, char ∗dest_url, globus_gass_copy_attr_t ∗dest_attr)
- globus_result_t **globus_gass_copy_register_url_to_url** (globus_gass_copy_handle_t ∗handle, char ∗source_url, globus_gass_copy_attr_t ∗source_attr, char ∗dest_url, globus_gass_copy_attr_t ∗dest_attr, globus_gass_copy_callback_t callback_func, void ∗callback_arg)
- globus_result_t **globus_gass_copy_register_url_to_handle** (globus_gass_copy_handle_t ∗handle, char ∗source_url, globus_gass_copy_attr_t ∗source_attr, globus_io_handle_t ∗dest_handle, globus_gass_copy_callback_t callback_func, void ∗callback_arg)
- globus_result_t **globus_gass_copy_register_handle_to_url** (globus_gass_copy_handle_t ∗handle, globus_io_handle_t ∗source_handle, char ∗dest_url, globus_gass_copy_attr_t ∗dest_attr, globus_gass_copy_callback_t callback_func, void ∗callback_arg)
- globus_result_t **globus_gass_copy_cache_url_state** (globus_gass_copy_handle_t ∗handle, char ∗url)
- globus_result_t **globus_gass_copy_flush_url_state** (globus_gass_copy_handle_t ∗handle, char ∗url)
- globus_result_t **globus_gass_copy_set_user_pointer** (globus_gass_copy_handle_t ∗handle, void ∗user_pointer)
- globus_result_t **globus_gass_copy_get_user_pointer** (globus_gass_copy_handle_t ∗handle, void ∗∗user_data)
- globus_result_t **globus_gass_copy_cancel** (globus_gass_copy_handle_t ∗handle, globus_gass_copy_callback_t cancel_callback, void ∗cancel_callback_arg)
- globus_result_t **globus_l_gass_copy_target_cancel** (**globus_i_gass_copy_cancel_t** ∗cancel_info)

5.1.1 Detailed Description

Globus GASS Copy library.

See also

See the detailed description in **globus_gass_copy.h** (p. 19)

5.1.2 Function Documentation

5.1.2.1 globus_result_t globus_gass_copy_handle_init (globus_gass_copy_handle_t * *handle,* globus_gass_copy_handleattr_t * *attr*)

Initialize a GASS Copy handle.

A globus_gass_copy_handle must be initialized before any transfers may be associated with it. This function initializes a globus_gass_copy_handle to be used for doing transfers, this includes initializing a globus_ftp_client_handle which will be used for doing any ftp/gsiftp transfers. The same handle may be used to perform multiple, consecutive transfers. However, there can only be one transfer associated with a particular handle at any given time. After all transfers to be associated with this handle have completed, the handle should be destroyed by calling **globus_gass_copy_handle_destroy()** (p. 8).

Parameters

handle	The handle to be initialized
attr	The handle attributes used to use with this handle

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_handle_destroy() (p. 8) , globus_gass_copy_handleattr_init(), globus_ftp_client_handle_init()

References GLOBUS_GASS_COPY_MODULE.

5.1.2.2 globus_result_t globus_gass_copy_handle_destroy (globus_gass_copy_handle_t * *handle*)

Destroy a GASS Copy handle.

Destroy a gass_copy_handle, which was initialized using **globus_gass_copy_handle_init()** (p. 8), that will no longer be used for doing transfers. Once the handle is detroyed, no further transfers should be associated with it.

Parameters

handle	The handle to be destroyed

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_handle_init() (p. 8), globus_ftp_client_handle_destroy()

References GLOBUS_GASS_COPY_MODULE.

5.1.2.3 globus_result_t globus_gass_copy_set_buffer_length (globus_gass_copy_handle_t * *handle,* int *length*)

Set the size of the buffer to be used for doing transfers.

This function allows the user to set the size of the buffer that will be used for doing transfers, if this function is not called the buffer size will default to 1M.

Parameters

handle	Set the buffer length for transfers associated with this handle.
length	The length, in bytes, to make the buffer.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.4 globus_result_t globus_gass_copy_get_buffer_length (globus_gass_copy_handle_t * *handle,* int * *length*)

Get the size of the buffer being used for doing transfers.

This function allows the user to get the size of the buffer that is being used for doing transfers.

Parameters

handle	Get the buffer length for transfers associated with this handle.
length	The length, in bytes, of the buffer.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.5 globus_result_t globus_gass_copy_set_no_third_party_transfers (globus_gass_copy_handle_t * *handle,* globus_bool_t *no_third_party_transfers*)

Turn third-party transfers on or off.

(They are on by default.)

This function allows the user to turn third-party transfers on or off for ftp to ftp transfers associated with a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

Parameters

handle	Turn third-party transfers on or off for transfers associated with this handle. They are on by default.
no_third_party_transfers	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References globus_gass_copy_get_status(), and GLOBUS_GASS_COPY_MODULE.

5.1.2.6 globus_result_t globus_gass_copy_get_no_third_party_transfers (globus_gass_copy_handle_t * *handle,* globus_bool_t * *no_third_party_transfers*)

See if third-party transfers are turned on or off.

(They are on by default.)

This function allows the user to see if third-party transfers are turned on or off for ftp to ftp transfers associated with

a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

Parameters

handle	See if third-party transfers are turned on or off for transfers associated with this handle. They are on by default.
no_third_party_transfers	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.7 globus_result_t globus_gass_copy_set_allocate (globus_gass_copy_handle_t * *handle*, globus_bool_t *send_allo*)

Set allo on or off.

5.1.2.8 globus_result_t globus_gass_copy_set_stat_on_expand (globus_gass_copy_handle_t * *handle*, globus_bool_t *always_stat*)

Make globus_gass_copy_expand_url() always send stat info.

5.1.2.9 globus_result_t globus_gass_copy_set_partial_offsets (globus_gass_copy_handle_t * *handle*, globus_off_t *offset*, globus_off_t *end_offset*)

Set the offsets to be used for doing partial transfers.

This function allows the user to set the offsets that will be used for doing partial transfers. An offset of -1 will disable partial transfers. An end_offset of -1 means EOF.

Parameters

handle	Set the offsets for partial transfers associated with this handle.
offset	The starting offset for the partial transfer.
end_offset	The ending offset for the partial transfer.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.10 globus_result_t globus_gass_copy_get_partial_offsets (globus_gass_copy_handle_t * *handle*, globus_off_t * *offset*, globus_off_t * *end_offset*)

Get the offsets being used for doing partial transfers.

This function allows the user to get the offsets that are being used for doing partial transfers. An offset of -1 means partial transfers are disabled.

Parameters

handle	Get the offsets for partial transfers associated with this handle.
offset	The starting offset for the partial transfer.
end_offset	The ending offset for the partial transfer.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.11 globus_result_t globus_gass_copy_attr_init (globus_gass_copy_attr_t * *attr*)

Initialize an attribute structure.

The globus_gass_copy_attr_t can be used to pass the globus_gass_copy library information about how a transfer should be performed. It must first be initialized by calling this function. Then any or all of the following functions may be called to set attributes associated with a particular protocol: **globus_gass_copy_attr_set_ftp()** (p. 11), **globus_gass_copy_attr_set_gass()** (p. 12), **globus_gass_copy_attr_set_io()** (p. 12). Any function which takes a globus_gass_copy_attr_t as an argument will also accept GLOBUS_NULL, in which case the appropriate set of default attributes will be used.

Parameters

attr	The attribute structure to be initialized

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_attr_set_ftp() (p. 11), **globus_gass_copy_attr_set_gass()** (p. 12), **globus_gass_copy_attr_set_io()** (p. 12), **globus_gass_copy_get_url_mode()** (p. 12).

References GLOBUS_GASS_COPY_MODULE.

5.1.2.12 globus_result_t globus_gass_copy_attr_set_ftp (globus_gass_copy_attr_t * *attr,* globus_ftp_client_operationattr_t * *ftp_attr*)

Set the attributes for ftp/gsiftp transfers.

In order to specify attributes for ftp/gsiftp transfers, a globus_ftp_client_operationattr_t should be initialized and its values set using the appropriate globus_ftp_client_operationattr_* functions. The globus_ftp_client_operationattr_t * can then be passed to the globus_gass_copy_attr_t via this function.

Parameters

attr	A globus_gass_copy attribute structure
ftp_attr	The ftp/gsiftp attributes to be used

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_attr_init() (p. 11), **globus_gass_copy_attr_set_gass()** (p. 12), **globus_gass_copy_attr_set_io()** (p. 12), **globus_gass_copy_get_url_mode()** (p. 12), globus_ftp_client_operationattr_*

References GLOBUS_GASS_COPY_MODULE.

5.1.2.13 globus_result_t globus_gass_copy_attr_set_io (globus_gass_copy_attr_t * *attr*, globus_io_attr_t * *io_attr*)

Set the attributes for file transfers.

In order to specify attributes for file transfers, a globus_io_attr_t should be initialized and its values set using the appropriate globus_io_attr_* functions. The globus_io_attr_t can then be passed to the globus_gass_copy_attr_t via this function.

Parameters

attr	A globus_gass_copy attribute structure
io_attr	The file attributes to be used

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_attr_init() (p. 11), **globus_gass_copy_attr_set_gass()** (p. 12), **globus_gass_copy_attr_set_ftp()** (p. 11), **globus_gass_copy_get_url_mode()** (p. 12), globus_io_attr_*

References GLOBUS_GASS_COPY_MODULE.

5.1.2.14 globus_result_t globus_gass_copy_attr_set_gass (globus_gass_copy_attr_t * *attr*, globus_gass_transfer_requestattr_t * *gass_attr*)

Set the attributes for http/https transfers.

In order to specify attributes for http/https transfers, a globus_gass_transfer_requestattr_t should be initialized and its values set using the appropriate globus_gass_transfer_requestattr_* functions. The globus_gass_transfer_requestattr_t can then be passed to the globus_gass_copy_attr_t via this function.

Parameters

attr	A globus_gass_copy attribute structure
gass_attr	The http/https attributes to be used

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_attr_init() (p. 11), **globus_gass_copy_attr_set_io()** (p. 12), **globus_gass_copy_attr_set_ftp()** (p. 11), **globus_gass_copy_get_url_mode()** (p. 12), globus_gass_transfer_requestattr_*

References GLOBUS_GASS_COPY_MODULE.

5.1.2.15 globus_result_t globus_gass_copy_get_url_mode (char * *url*, globus_gass_copy_url_mode_t * *mode*)

Classify the URL schema into the transfer method that will be used to do the actual tranfer.

This function enables the user to determine what protocol will be used to transfer data to/from a particular url. This information can then be used to specify the appropriate attributes when initiating a transfer.

Parameters

url	The URL for schema checking
mode	the filled in schema type of the URL param

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

See also

globus_gass_copy_attr_init() (p. 11), **globus_gass_copy_attr_set_io()** (p. 12), **globus_gass_copy_attr_set_ftp()** (p. 11), globus_gass_copy_set_gass()

References GLOBUS_GASS_COPY_MODULE.

5.1.2.16 globus_result_t globus_gass_copy_register_performance_cb (globus_gass_copy_handle_t * *handle*, globus_gass_copy_performance_cb_t *callback*, void * *user_arg*)

Register a performance information callback.

Use this to register a performance information callback. You change or set to GLOBUS_NULL the callback any time a transfer is not occurring.

Parameters

handle	an initialized gass copy handle for which you would like to see performance info
callback	the performance callback
user_arg	a user pointer that will be passed to all callbacks for a given handle

Returns

- GLOBUS_SUCCESS
- error on a NULL or busy handle

See also

globus_gass_copy_performance_cb_t (p. 20)

References GLOBUS_GASS_COPY_MODULE.

5.1.2.17 globus_result_t globus_gass_copy_get_status (globus_gass_copy_handle_t * *handle*, globus_gass_copy_status_t * *status*)

Get the status code of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLOBUS_GASS_COPY_STATUS_NONE, GLOBUS_GASS_COPY_STATUS_DONE_SUCCESS, GLOBUS_GASS_COPY_STATUS_DONE_FAILURE, GLOBUS_GASS_COPY_STATUS_DONE_CANCELLED

Parameters

handle	A globus_gass_copy_handle
status	Will be one of the following: GLOBUS_GASS_COPY_STATUS_NONE (No transfers have been initiated using this handle.) GLOBUS_GASS_COPY_STATUS_PENDING (A transfer is currently being set up.) GLOBUS_GASS_COPY_STATUS_TRANSFER_IN_PROGRESS (There is currently a transfer in progress.) GLOBUS_GASS_COPY_STATUS_CANCEL (The last transfer initiated using this handle has been cancelled by the user before completing, and is in the process of being cleaned up.) GLOBUS_GASS_COPY_STATUS_FAILURE (The last transfer initiated using this handle failed, and is in the process of being cleaned up.) - GLOBUS_GASS_COPY_STATUS_DONE_SUCCESS (The last transfer initiated using this handle has completed successfully.) GLOBUS_GASS_COPY_STATUS_DONE_FAILURE (- The last transfer initiated using this handle failed and has finished cleaning up.) GLOBUS_G-ASS_COPY_STATUS_DONE_CANCELLED (The last transfer initiated using this handle was cancelled and has finished cleaning up.)

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.18 const char* globus_gass_copy_get_status_string (globus_gass_copy_handle_t * *handle*)

Get the status string of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLO-BUS_GASS_COPY_STATUS_NONE, GLOBUS_GASS_COPY_STATUS_DONE_SUCCESS, GLOBUS_GASS_-COPY_STATUS_DONE_FAILURE, GLOBUS_GASS_COPY_STATUS_DONE_CANCELLED

Parameters

handle	A globus_gass_copy_handle

Returns

Returns a pointer to a character string describing the current status

References globus_gass_copy_get_status().

5.1.2.19 globus_result_t globus_gass_copy_url_to_url (globus_gass_copy_handle_t * *handle*, char * *source_url*, globus_gass_copy_attr_t * *source_attr*, char * *dest_url*, globus_gass_copy_attr_t * *dest_attr*)

Transfer data from source URL to destination URL (blocking)

Parameters

handle	The handle to perform the copy operation
source_url	transfer data from this URL
source_attr	Attributes describing how the transfer form the source should be done
dest_url	transfer data to this URL
dest_attr	Attributes describing how the transfer to the destination should be done

Returns

This function returns GLOBUS_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_url_to_handle() (p. 15) **globus_gass_copy_handle_to_url()** (p. 15)

References GLOBUS_GASS_COPY_MODULE, and globus_gass_copy_register_url_to_url().

5.1.2.20 globus_result_t globus_gass_copy_url_to_handle (globus_gass_copy_handle_t * *handle*, char * *source_url*, globus_gass_copy_attr_t * *source_attr*, globus_io_handle_t * *dest_handle*)

Transfer data from source URL to an IO handle (blocking)

Parameters

handle	The handle to perform the copy operation
source_url	transfer data from this URL
source_attr	Attributes describing how the transfer form the source should be done
dest_handle	transfer data to this IO handle

Returns

This function returns GLOBUS_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_url_to_url() (p. 14) **globus_gass_copy_handle_to_url()** (p. 15)

References GLOBUS_GASS_COPY_MODULE, and globus_gass_copy_register_url_to_handle().

5.1.2.21 globus_result_t globus_gass_copy_handle_to_url (globus_gass_copy_handle_t * *handle*, globus_io_handle_t * *source_handle*, char * *dest_url*, globus_gass_copy_attr_t * *dest_attr*)

Transfer data from an IO handle to destination URL (blocking)

Parameters

handle	The handle to perform the copy operation
source_handle	transfer data from this IO handle
dest_url	transfer data to this URL
dest_attr	Attributes describing how the transfer to the destination should be done

Returns

This function returns GLOBUS_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_url_to_url() (p. 14) **globus_gass_copy_url_to_handle()** (p. 15)

References GLOBUS_GASS_COPY_MODULE, and globus_gass_copy_register_handle_to_url().

5.1.2.22 globus_result_t globus_gass_copy_register_url_to_url (globus_gass_copy_handle_t * *handle*, char * *source_url*, globus_gass_copy_attr_t * *source_attr*, char * *dest_url*, globus_gass_copy_attr_t * *dest_attr*, globus_gass_copy_callback_t *callback_func*, void * *callback_arg*)

Transfer data from source URL to destination URL (non-blocking)

This functions initiates a transfer from source URL to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the callback_func will be invoked with the final status of the transfer.

Parameters

handle	The handle to perform the copy operation
source_url	transfer data from this URL
source_attr	Attributes describing how the transfer form the source should be done
dest_url	transfer data to this URL
dest_attr	Attributes describing how the transfer to the destination should be done
callback_func	Callback to be invoked once the transfer is completed.
callback_arg	Argument to be passed to the callback_func.

Returns

This function returns GLOBUS_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.

GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_register_url_to_handle() (p. 17), **globus_gass_copy_register_handle_to_url()** (p. 17)

References GLOBUS_GASS_COPY_MODULE, globus_gass_copy_get_url_mode(), globus_gass_copy_state_s::cancel, globus_gass_copy_state_s::source, globus_gass_copy_state_s::dest, and globus_i_gass_copy_state_target_s::attr.

5.1.2.23 globus_result_t globus_gass_copy_register_url_to_handle (globus_gass_copy_handle_t * *handle*, char * *source_url*, globus_gass_copy_attr_t * *source_attr*, globus_io_handle_t * *dest_handle*, globus_gass_copy_callback_t *callback_func*, void * *callback_arg*)

Transfer data from source URL to an IO handle (non-blocking)

This functions initiates a transfer from source URL to an IO handle, then returns immediately.

When the transfer is completed or if the transfer is aborted, the callback_func will be invoked with the final status of the transfer.

Parameters

handle	The handle to perform the copy operation
source_url	transfer data from this URL
source_attr	Attributes describing how the transfer form the source should be done
dest_handle	transfer data to this IO handle
callback_func	Callback to be invoked once the transfer is completed.
callback_arg	Argument to be passed to the callback_func.

Returns

This function returns GLOBUS_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_register_url_to_url() (p. 16), **globus_gass_copy_register_handle_to_url()** (p. 17)

References GLOBUS_GASS_COPY_MODULE, globus_gass_copy_get_url_mode(), globus_gass_copy_state_s::cancel, globus_gass_copy_state_s::source, and globus_gass_copy_state_s::dest.

5.1.2.24 globus_result_t globus_gass_copy_register_handle_to_url (globus_gass_copy_handle_t * *handle*, globus_io_handle_t * *source_handle*, char * *dest_url*, globus_gass_copy_attr_t * *dest_attr*, globus_gass_copy_callback_t *callback_func*, void * *callback_arg*)

Transfer data from an IO handle to destination URL (non-blocking)

This functions initiates a transfer from an IO handle to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the callback_func will be invoked with the final status of the transfer.

Parameters

handle	The handle to perform the copy operation
source_handle	transfer data from this IO handle
dest_url	transfer data to this URL
dest_attr	Attributes describing how the transfer to the destination should be done
callback_func	Callback to be invoked once the transfer is completed.
callback_arg	Argument to be passed to the callback_func.

Returns

This function returns GLOBUS_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

Return values

GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
GLOBUS_GASS_COPY_ERROR_TYPE_next_error	next error description

See also

globus_gass_copy_register_url_to_url() (p. 16), **globus_gass_copy_register_url_to_handle()** (p. 17)

References GLOBUS_GASS_COPY_MODULE, globus_gass_copy_get_url_mode(), globus_gass_copy_state_s::cancel, globus_gass_copy_state_s::source, and globus_gass_copy_state_s::dest.

5.1.2.25 globus_result_t globus_gass_copy_cache_url_state (globus_gass_copy_handle_t * *handle*, char * *url*)

Cache connections to an FTP or GSIFTP server.

Explicitly cache connections to URL server. When an URL is cached, the connection to the URL server will not be closed after a file transfer completes.

Parameters

handle	Handle which will contain a cached connection to the URL server.
url	The URL of the FTP or GSIFTP server to cache.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.26 globus_result_t globus_gass_copy_flush_url_state (globus_gass_copy_handle_t * *handle*, char * *url*)

Remove a cached connection to an FTP or GSIFTP server.

Explicitly remove a cached connection to an FTP or GSIFTP server. If an idle connection to an FTP server exists, it will be closed.

Parameters

handle	Handle which contains a cached connection to the URL server.
url	The URL of the FTP or GSIFTP server to remove.

Returns

This function returns GLOBUS_SUCCESS if successful, or a globus_result_t indicating the error that occurred.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.27 globus_result_t globus_gass_copy_set_user_pointer (globus_gass_copy_handle_t * *handle,* void * *user_pointer*)

Set a pointer in the handle to point at user-allocated memory.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.28 globus_result_t globus_gass_copy_get_user_pointer (globus_gass_copy_handle_t * *handle,* void ** *user_data*)

Get the pointer in the handle that points to user-allocated memory.

References GLOBUS_GASS_COPY_MODULE.

5.1.2.29 globus_result_t globus_gass_copy_cancel (globus_gass_copy_handle_t * *handle,* globus_gass_copy_callback_t *cancel_callback,* void * *cancel_callback_arg*)

Cancel the current transfer associated with this handle,.

store the cancel_callback and cancel_callback_arg in the handle. Needed because the ftp callback will be the one given from the original globus_ftp_client_third_party_transfer() call.

References GLOBUS_GASS_COPY_MODULE, and globus_l_gass_copy_target_cancel().

5.1.2.30 globus_result_t globus_l_gass_copy_target_cancel (globus_i_gass_copy_cancel_t * *cancel_info*)

Cancel the source or destination transfer in progress.

References globus_i_gass_copy_state_target_s::mode, globus_i_gass_copy_state_target_s::data, globus_i_gass_copy_state_target_s::ftp, globus_i_gass_copy_state_target_s::gass, GLOBUS_GASS_COPY_MODULE, globus_i_gass_copy_state_target_s::url, and globus_i_gass_copy_state_target_s::io.

5.2 globus_gass_copy.h File Reference

Data Structures

- struct **globus_gass_copy_glob_stat_t**
  Glob expanded entry information.

Defines

- #define **GLOBUS_GASS_COPY_MODULE** (&globus_i_gass_copy_module)

Typedefs

- typedef void(* **globus_gass_copy_performance_cb_t**)(void *user_arg, globus_gass_copy_handle_t *handle, globus_off_t total_bytes, float instantaneous_throughput, float avg_throughput)
- typedef void(* **globus_gass_copy_glob_entry_cb_t**)(const char *url, const **globus_gass_copy_glob_stat_t** *info_stat, void *user_arg)

Enumerations

- enum **globus_gass_copy_glob_entry_t**

Functions

- globus_result_t **globus_gass_copy_glob_expand_url** (globus_gass_copy_handle_t *handle, const char *url, globus_gass_copy_attr_t *attr, **globus_gass_copy_glob_entry_cb_t** entry_cb, void *user_arg)
- globus_result_t **globus_gass_copy_mkdir** (globus_gass_copy_handle_t *handle, char *url, globus_gass_copy_attr_t *attr)

5.2.1 Detailed Description

Header file for the gass copy library.

5.2.2 Define Documentation

5.2.2.1 #define GLOBUS_GASS_COPY_MODULE (&globus_i_gass_copy_module)

Module descriptor.

Globus GASS Copy uses standard Globus module activation and deactivation. Before any Globus GASS Copy functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GASS_COPY_MODULE)
```

This function returns GLOBUS_SUCCESS if Globus GASS Copy was successfully initialized, and you are therefore allowed to subsequently call Globus GASS Copy functions. Otherwise, an error code is returned, and Globus GASS Copy functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GASS Copy, the following function must be called:

```
globus_module_deactivate(GLOBUS_GASS_COPY_MODULE)
```

This function should be called once for each time Globus GASS Copy was activated.

5.2.3 Typedef Documentation

5.2.3.1 typedef void(* globus_gass_copy_performance_cb_t)(void *user_arg, globus_gass_copy_handle_t *handle, globus_off_t total_bytes, float instantaneous_throughput, float avg_throughput)

Gass copy transfer performance callback.

This callback is registered with 'globus_gass_copy_register_performance_cb' It will be called during a transfer to supply performance information on current transfer. Its frequency will be at most one per second, but it is possible to receive no callbacks. This is possible in very short transfers and in ftp transfers in which the server does not provide performance information.

Parameters

handle	the gass copy handle this transfer is occurring on
user_arg	a user pointer registered with 'globus_gass_copy_register_performance_cb'
total_bytes	the total number of bytes transfer so far
instantaneous_throughput	instantaneous rate of transfer (since last callback or start) (bytes / sec)
avg_throughput	the avg thoughput calculated since the start of the transfer (bytes / sec)

Returns

- n/a

5.2.3.2 typedef void(* globus_gass_copy_glob_entry_cb_t)(const char *url, const globus_gass_copy_glob_stat_t *info_stat, void *user_arg)

Gass copy glob entry callback.

This callback is passed as a parameter to **globus_gass_copy_glob_expand_url()** (p. 21). It is called once for each entry that the original expands to.

Parameters

url	The full url to the expanded entry. A directory entry will end in a forward slash '/'.
stat	A pointer to a **globus_gass_copy_glob_stat_t** (p. 3) containing information about the entry.
user_arg	The user_arg passed to globus_gass_copy_glob_expand()

See also

globus_gass_copy_glob_stat_t (p. 3), **globus_gass_copy_glob_expand_url** (p. 21)

5.2.4 Enumeration Type Documentation

5.2.4.1 enum globus_gass_copy_glob_entry_t

globbed entry types

5.2.5 Function Documentation

5.2.5.1 globus_result_t globus_gass_copy_glob_expand_url (globus_gass_copy_handle_t * *handle*, const char * *url*, globus_gass_copy_attr_t * *attr*, globus_gass_copy_glob_entry_cb_t *entry_cb*, void * *user_arg*)

Expand globbed url.

This function expands wildcards in a globbed url, and calls entry_cb() on each one.

Parameters

handle	A gass copy handle to use for the operation.
url	The URL to expand. The URL may be an ftp, gsiftp or file URL. Wildcard characters supported are '?' '*' '[ ]' in the filename portion of the url.
attr	Gass copy attributes for this operation.
entry_cb	Function to call with information about each entry
user_arg	An argument to pass to entry_cb()

Returns

This function returns an error when any of these conditions are true:

- handle is GLOBUS_NULL
- url is GLOBUS_NULL
- url cannot be parsed
- url is not a ftp, gsiftp or file url

References globus_gass_copy_glob_expand_url(), GLOBUS_GASS_COPY_MODULE, globus_gass_copy_glob_stat_t::symlink_target, globus_gass_copy_glob_stat_t::unique_id, globus_gass_copy_glob_stat_t::type, globus_gass_copy_glob_stat_t::mode, globus_gass_copy_glob_stat_t::mdtm, and globus_gass_copy_glob_stat_t::size.

5.2.5.2 globus_result_t globus_gass_copy_mkdir (globus_gass_copy_handle_t * *handle*, char * *url*, globus_gass_copy_attr_t * *attr*)

Make directory.

This function creates a directory given a ftp or file url.

Parameters

handle	A gass copy handle to use for the mkdir operation.
url	The URL for the directory to create. The URL may be an ftp, gsiftp or file URL.
attr	Gass copy attributes for this operation.

Returns

This function returns an error when any of these conditions are true:

- handle is GLOBUS_NULL
- url is GLOBUS_NULL
- url cannot be parsed
- url is not a ftp, gsiftp or file url
- the directory could not be created

References globus_gass_copy_mkdir(), globus_gass_copy_get_url_mode(), and GLOBUS_GASS_COPY_MODULE.