globus gss assist

8.1

Generated by Doxygen 1.7.4

Tue Feb 14 2012 16:07:19

Contents

1 Globus GSI GSS Assist **1**

2 Module Index **1**

2.1 Modules 1

3 Module Documentation **1**

3.1 Activation 1

3.1.1 Detailed Description 2

3.1.2 Define Documentation 2

3.2 Utility Functions 2

3.2.1 Detailed Description 4

3.2.2 Define Documentation 4

3.2.3 Function Documentation 4

3.3 GSI GSS Assist Constants 13

3.3.1 Enumeration Type Documentation 14

3.4 Security Token Transport 15

3.4.1 Detailed Description 15

3.4.2 Function Documentation 15

1 Globus GSI GSS Assist

The GSS Assist code provides convenience functions for using the Globus GSS-API.

2 Module Index

2.1 Modules

Here is a list of all modules:

Activation **1**

Utility Functions **2**

GSI GSS Assist Constants **13**

Security Token Transport **15**

3 Module Documentation

3.1 Activation

Globus GSI GSS Assist uses standard Globus module activation and deactivation.

Defines

- #define **GLOBUS_GSI_GSS_ASSIST_MODULE**

3.1.1 Detailed Description

Globus GSI GSS Assist uses standard Globus module activation and deactivation. Before any Globus GSS Assist functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_GSS_ASSIST_MODULE);
```

This function returns GLOBUS_SUCCESS if Globus GSI GSS Assist was successfully initialized, and you are therefore allowed to call GSS Assist functions. Otherwise, an error code is returned, and GSS Assist functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSS Assist, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_GSS_ASSIST_MODULE)
```

This function should be called once for each time Globus GSI GSS Assist was activated.

3.1.2 Define Documentation

3.1.2.1 #define GLOBUS_GSI_GSS_ASSIST_MODULE

Module descriptor.

3.2 Utility Functions

Utility functions for GSSAPI.

Defines

- #define **GlobusGssAssistFreeDNArray**(dn_a)
- #define **NI_MAXHOST** 255

Functions

- int **globus_gss_assist_gridmap** (char *globusidp, char **useridp)
- int **globus_gss_assist_userok** (char *globusid, char *userid)
- int **globus_gss_assist_map_local_user** (char *local_user, char **globusidp)
- globus_result_t **globus_gss_assist_lookup_all_globusid** (char *username, char **dns[], int *dn_count)
- globus_result_t **globus_gss_assist_map_and_authorize** (gss_ctx_id_t context, char *service, char *desired_identity, char *identity_buffer, unsigned int identity_buffer_length)

Accept Security Context

- OM_uint32 **globus_gss_assist_accept_sec_context** (OM_uint32 *minor_status, gss_ctx_id_t *context_handle, const gss_cred_id_t cred_handle, char **src_name_char, OM_uint32 *ret_flags, int *user_to_user_flag, int *token_status, gss_cred_id_t *delegated_cred_handle, int(*gss_assist_get_token)(void *, void **, size_t *), void *gss_assist_get_context, int(*gss_assist_send_token)(void *, void *, size_t), void *gss_assist_send_context)

Accept Security Context Asyncronous

- OM_uint32 **globus_gss_assist_accept_sec_context_async** (OM_uint32 *minor_status, gss_ctx_id_t *context_handle, const gss_cred_id_t cred_handle, char **src_name_char, OM_uint32 *ret_flags, int *user_to_user_flag, void *input_buffer, size_t input_buffer_len, void **output_bufferp, size_t *output_buffer_lenp, gss_cred_id_t *delegated_cred_handle)

Acquire Credential

- OM_uint32 **globus_gss_assist_acquire_cred** (OM_uint32 *minor_status, gss_cred_usage_t cred_usage, gss_cred_id_t *output_cred_handle)

Acquire Credential Extension

- OM_uint32 **globus_gss_assist_acquire_cred_ext** (OM_uint32 *minor_status, char *desired_name_char, OM_uint32 time_req, const gss_OID_set desired_mechs, gss_cred_usage_t cred_usage, gss_cred_id_t *output_cred_handle, gss_OID_set *actual_mechs, OM_uint32 *time_rec)

Display Status

- OM_uint32 **globus_gss_assist_display_status** (FILE *fp, char *comment, OM_uint32 major_status, OM_uint32 minor_status, int token_status)

Display Status String

- OM_uint32 **globus_gss_assist_display_status_str** (char **str, char *comment, OM_uint32 major_status, OM_uint32 minor_status, int token_status)

- OM_uint32 **globus_gss_assist_import_sec_context** (OM_uint32 *minor_status, gss_ctx_id_t *context_handle, int *token_status, int fdp, FILE *fperr)

Init Security Context

- OM_uint32 **globus_gss_assist_init_sec_context** (OM_uint32 *minor_status, const gss_cred_id_t cred_handle, gss_ctx_id_t *context_handle, char *target_name_char, OM_uint32 req_flags, OM_uint32 *ret_flags, int *token_status, int(*gss_assist_get_token)(void *, void **, size_t *), void *gss_assist_get_context, int(*gss_assist_send_token)(void *, void *, size_t), void *gss_assist_send_context)

Init Security Context Async

- OM_uint32 **globus_gss_assist_init_sec_context_async** (OM_uint32 *minor_status, const gss_cred_id_t cred_handle, gss_ctx_id_t *context_handle, char *target_name_char, OM_uint32 req_flags, OM_uint32 *ret_flags, void *input_buffer, size_t input_buffer_len, void **output_bufferp, size_t *output_buffer_lenp)

Will Handle Restrictions

- OM_uint32 **globus_gss_assist_will_handle_restrictions** (OM_uint32 *minor_status, gss_ctx_id_t *context_handle)

Get Unwrap

- OM_uint32 **globus_gss_assist_get_unwrap** (OM_uint32 *minor_status, const gss_ctx_id_t context_handle, char **data, size_t *length, int *token_status, int(*gss_assist_get_token)(void *, void **, size_t *), void *gss_assist_get_context, FILE *fperr)

Wrap

- OM_uint32 **globus_gss_assist_wrap_send** (OM_uint32 *minor_status, const gss_ctx_id_t context_handle, char *data, size_t length, int *token_status, int(*gss_assist_send_token)(void *, void *, size_t), void *gss_assist_send_context, FILE *fperr)

3.2.1 Detailed Description

Utility functions for GSSAPI.

3.2.2 Define Documentation

3.2.2.1 #define GlobusGssAssistFreeDNArray(*dn_a*)

Free array of distinguished names.

Free the contents of a name array created during a successful call to **globus_gss_assist_lookup_all_globusid()** (p. 9)

Parameters

dn_a	Array of names to free.

Return values

void	

3.2.2.2 #define NI_MAXHOST 255

Create a GSS Name structure from the given hostname.

This function tries to resolve the given host name string to the canonical DNS name for the host.

Parameters

hostname	The host name or numerical address to be resolved and transform into a GSS Name
authorization_-hostname	The resulting GSS Name

Returns

GLOBUS_SUCCESS on successful completion, a error object otherwise

3.2.3 Function Documentation

3.2.3.1 OM_uint32 globus_gss_assist_accept_sec_context (OM_uint32 * *minor_status,* gss_ctx_id_t * *context_handle,* const gss_cred_id_t *cred_handle,* char ** *src_name_char,* OM_uint32 * *ret_flags,* int * *user_to_user_flag,* int * *token_status,* gss_cred_id_t * *delegated_cred_handle,* int(*)(void *, void **, size_t *) *gss_assist_get_token,* void * *gss_assist_get_context,* int(*)(void *, void *, size_t) *gss_assist_send_token,* void * *gss_assist_send_context*)

This routine accepts a GSSAPI security context and is called by the gram_gatekeeper.

It isolates the GSSAPI from the rest of the gram code.

Initialize a gssapi security connection. Used by the server. The context_handle is returned, and there is one for each connection. This routine will take cake of the looping and token processing, using the supplied get_token and send_token routines.

Parameters

minor_status	gssapi return code
context_handle	pointer to returned context.
cred_handle	the cred handle obtained by acquire_cred.
src_name_char	Pointer to char string repersentation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.
ret_flags	Pointer to which services are available after the connection is established. Maybe NULL if not wanted. We will also use this to pass in flags to the globus version of gssapi_ssleay
user_to_user_flag	Pointer to flag to be set if the src_name is the same as our name. (Follwing are particular to this assist routine)
token_status	assist routine get/send token status
delegated_cred_handle	pointer to be set to the credential delegated by the client if delegation occurs during the security handshake
gss_assist_get_token	a get token routine
gss_assist_get_context	first arg for the get token routine
gss_assist_send_token	a send token routine
gss_assist_send_context	first arg for the send token routine

Returns

GSS_S_COMPLETE on sucess Other gss errors on failure.

3.2.3.2 OM_uint32 globus_gss_assist_accept_sec_context_async (OM_uint32 * *minor_status,* gss_ctx_id_t * *context_handle,* const gss_cred_id_t *cred_handle,* char ** *src_name_char,* OM_uint32 * *ret_flags,* int * *user_to_user_flag,* void * *input_buffer,* size_t *input_buffer_len,* void ** *output_bufferp,* size_t * *output_buffer_lenp,* gss_cred_id_t * *delegated_cred_handle*)

This is a asynchronous version of the **globus_gss_assist_accept_sec_context()** (p. 5) function.

Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters

minor_status	gssapi return code
context_handle	pointer to returned context.
cred_handle	the cred handle obtained by acquire_cred.
src_name_char	Pointer to char string repersentation of the client which contacted the server. Maybe NULL if not wanted. Should be freed when done.
ret_flags	Pointer to which services are available after the connection is established. Maybe NULL if not wanted. We will also use this to pass in flags to the globus version of gssapi_ssleay

user_to_user_flag	Pointer to flag to be set if the src_name is the same as our name.
input_buffer	pointer to a buffer received from peer.
input_buffer_len	length of the buffer input_buffer.
output_bufferp	pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NULL the contents of this block should be written to the peer where they will be fed into the gss_assist_init_sec_context_async() function.
output_buffer_lenp	pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by ∗output_bufferp.
delegated_cred_handle	pointer to be set to the credential delegated by the client if delegation occurs during the security handshake

Returns

GSS_S_COMPLETE on successful completion when this function does not need to be called again.

GSS_S_CONTINUE_NEEDED when ∗output_bufferp should be sent to the peer and a new input_buffer read and this function called again.

Other gss errors on failure.

3.2.3.3 OM_uint32 globus_gss_assist_acquire_cred (OM_uint32 ∗ *minor_status,* gss_cred_usage_t *cred_usage,* gss_cred_id_t ∗ *output_cred_handle*)

Called once at the start of the process, to obtain the credentials the process is running under.

The

Parameters

minor_status	pointer for return code
cred_usage	GSS_C_INITIATE, GSS_C_ACCEPT, or GSS_C_BOTH
output_cred_handle	Pointer to the returned handle. This needs to be passed to many gss routines.

Returns

GSS_S_COMPLETE on sucess Other GSS return codes

3.2.3.4 OM_uint32 globus_gss_assist_acquire_cred_ext (OM_uint32 ∗ *minor_status,* char ∗ *desired_name_char,* OM_uint32 *time_req,* const gss_OID_set *desired_mechs,* gss_cred_usage_t *cred_usage,* gss_cred_id_t ∗ *output_cred_handle,* gss_OID_set ∗ *actual_mechs,* OM_uint32 ∗ *time_rec*)

Called once at the start of the process, to obtain the credentials the process is running under.

All the parameters of the gss_acquire_cred, except the desired_name is a string of the form: [type:]name. This will be imported with the type.

Returns

GSS_S_COMPLETE on sucess Other GSS return codes

See also

globus_gsi_gss_acquire_cred

3.2.3.5 OM_uint32 globus_gss_assist_display_status (FILE * *fp,* char * *comment,* OM_uint32 *major_status,* OM_uint32 *minor_status,* int *token_status*)

Display the messages for the major and minor status on the file pointed at by fp.

Takes care of the overloaded major_status if there was a problem with the get_token or send_token routines.

Parameters

fp	a file pointer
comment	String to print out before other error messages.
major_status	The major status to display
minor_status	The minor status to display
token_status	token status to display

Returns

0

3.2.3.6 OM_uint32 globus_gss_assist_display_status_str (char ** *str,* char * *comment,* OM_uint32 *major_status,* OM_uint32 *minor_status,* int *token_status*)

Display the messages for the major and minor status and return a string with the messages.

Takes care of the overloaded major_status if there was a problem with the get_token or send_token routines.

Parameters

str	pointer to char * for returned string. Must be freed
comment	String to print out before other error messages.
major_status	The major status to display
minor_status	The minor status to display
token_status	token status to display

Returns

0

3.2.3.7 int globus_gss_assist_gridmap (char * *globusidp,* char ** *useridp*)

Look up the default mapping for a Grid identity in a gridmap file.

The **globus_gss_assist_gridmap()** (p. 7) function parses the default gridmap file and modifies its *useridp* parameter to point to a copy of the string containing the default local identity that the grid identity is mapped to. If successful, the caller is responsible for freeing the string pointed to by *useridp*.

By default, **globus_gss_assist_gridmap()** (p. 7) looks for the default gridmap file defined by the value of the GRIDMAP environment variable. If that is not set, it falls back to $HOME/.gridmap.

Parameters

globusidp	The GSSAPI name string of the identity who requested authorization
useridp	A pointer to a string to be set to the default user ID for the local system. No validation is done to check that such a user exists.

Returns

On success, **globus_gss_assist_gridmap()** (p. 7) returns 0 and modifies the the string pointed to by the *useridp* parameter. If an error occurs, a non-zero value is returned and the value pointed to by *useridp* is undefined.

Return values

GLOBUS_SUCCESS	Success
1	Error

3.2.3.8 int globus_gss_assist_userok (char * *globusid,* char * *userid*)

Gridmap entry existence check.

The **globus_gss_assist_userok()** (p. 8) function parses the default gridmap file and checks whether any mapping exists for the grid identity passed as the *globusid* parameter and the local user identity passed as the @ userid parameter.

By default, **globus_gss_assist_userok()** (p. 8) looks for the default gridmap file defined by the value of the GRIDMAP environment variable. If that is not set, it falls back to $HOME/.gridmap.

Parameters

globusid	The GSSAPI name string of the identity who requested authorization
userid	The local account name that access is sought for.

Returns

If **globus_gss_assist_userok()** (p. 8) is able to find a mapping between *globusid* and *userid*, it returns 0; otherwise it returns 1.

Return values

GLOBUS_SUCCESS	Success
1	Error

3.2.3.9 int globus_gss_assist_map_local_user (char * *local_user,* char ** *globusidp*)

Look up the default Grid identity associated with a local user name.

The **globus_gss_assist_map_local_user()** (p. 8) function parses the gridmap file to determine a if the user name passed as the *local_user* parameter is the default local user for a Grid ID in the gridmap file. If so, it modifies *globusidp* to point to a copy of that ID. Otherwise, it searches the gridmap file for a Grid ID that has a non-default mapping for *local_user* and modifies *globusidp* to point to a copy of that ID. If successful, the caller is responsible for freeing the string pointed to by the *globusidp* pointer.

By default, **globus_gss_assist_map_local_user()** (p. 8) looks for the default gridmap file defined by the value of the GRIDMAP environment variable. If that is not set, it falls back to $HOME/.gridmap.

Parameters

local_user	The local username to find a Grid ID for
globusidp	A Grid ID that maps from the local_user.

Returns

On success, **globus_gss_assist_map_local_user()** (p. 8) returns 0 and modifies *globusidp* to point to a Grid ID that maps to *local_user*; otherwise, **globus_gss_assist_map_local_user()** (p. 8) returns 1 and the value pointed to by *globusidp* is undefined.

Return values

GLOBUS_SUCCESS	Success
1	Error

3.2.3.10 globus_result_t globus_gss_assist_lookup_all_globusid (char * *username*, char ** *dns[]*, int * *dn_count*)

Look up all Grid IDs associated with a local user ID.

The **globus_gss_assist_lookup_all_globusid()** (p. 9) function parses a gridmap file and finds all Grid IDs that map to a local user ID. The *dns* parameter is modified to point to an array of Grid ID strings from the gridmap file, and the *dn_count* parameter is modified to point to the number of Grid ID strings in the array. The caller is responsible for freeing the array using the macro ***GlobusGssAssistFreeDNArray()*** *(*p. *4)*.

By default, **globus_gss_assist_lookup_all_globusid()** (p. 9) looks for the default gridmap file defined by the value of the GRIDMAP environment variable. If that is not set, it falls back to $HOME/.gridmap.

Parameters

username	The local username to look up in the gridmap file.
dns	A pointer to an array of strings. This function modifies this to point to a newly allocated array of strings. The caller must use the macro ***GlobusGssAssistFreeDNArray()*** *(*p. *4)* to free this memory.
dn_count	A pointer to an integer that is modified to contain the number of entries in the array returned via the *dns* parameter.

Returns

On success, **globus_gss_assist_lookup_all_globusid()** (p. 9) returns GLOBUS_SUCCESS and modifies its *dns* and *dn_count* parameters as described above. If an error occurs, **globus_gss_assist_lookup_all_globusid()** (p. 9) returns a globus_result_t that can be resolved to an error object and the values pointed to by *dns* and *dn_count* are undefined.

Return values

GLOBUS_SUCCESS	Success
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS	Error with arguments
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP	Invalid path to gridmap
GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO	System error

3.2.3.11 globus_result_t globus_gss_assist_map_and_authorize (gss_ctx_id_t *context*, char * *service*, char * *desired_identity*, char * *identity_buffer*, unsigned int *identity_buffer_length*)

Authorize the peer of a security context to use a service.

The **globus_gss_assist_map_and_authorize()** (p. 9) function attempts to authorize the peer of a security context to use a particular service. If the *desired_identity* parameter is non-NULL, the authorization will succeed only if the peer is authorized for that identity. Otherwise, any valid authorized local user name will be used. If authorized, the local user name will be copied to the string pointed to by the *identity_buffer* parameter, which must be at least as long as the value passed as the *identity_buffer_length* parameter.

If authorization callouts are defined in the callout configuration file, **globus_gss_assist_map_and_authorize()** (p. 9) will invoke both the GLOBUS_GENERIC_MAPPING_TYPE callout and the GLOBUS_GENERIC_AUTHZ_TYPE callout; otherwise the default gridmap file will be used for mapping and no service-specific authorization will be done.

If **globus_gss_assist_map_and_authorize()** (p. 9) uses a gridmap file, it first looks for a file defined by the value of the GRIDMAP environment variable. If that is not set, it falls back to $HOME/.gridmap.

Parameters

context	Security context to inspect for peer identity information.
service	A NULL-terminated string containing the name of the service that an authorization decision is being made for.
desired_identity	Optional. If non-NULL, perform an authorization to act as the local user named by this NULL-terminated string.
identity_buffer	A pointer to a string buffer into which will be copied the local user name that the peer of the context is authorized to act as.
identity_buffer_length	Length of the *identity_buffer* array.

Returns

On success, **globus_gss_assist_map_and_authorize()** (p. 9) returns GLOBUS_SUCCESS and copies the authorized local identity to the *identity_buffer* parameter. If an error occurs, **globus_gss_assist_map_and_authorize()** (p. 9) returns a globus_result_t that can be resolved to an error object.

Return values

GLOBUS_SUCCESS	Success
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG	Invalid authorization configuration file
GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE	Hash table operation failed.
GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR	The callout itself returned a error.
GLOBUS_CALLOUT_ERROR_WITH_DL	Dynamic library operation failed.
GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY	Out of memory
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR	A GSSAPI function returned an error
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED	Gridmap lookup failure
GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL	Caller provided insufficient buffer space for local identity

3.2.3.12 OM_uint32 globus_gss_assist_import_sec_context (OM_uint32 * *minor_status,* gss_ctx_id_t * *context_handle,* int * *token_status,* int *fdp,* FILE * *fperr*)

Import the security context from a file.

Parameters

minor_status	GSSAPI return code. This is a Globus Error code (or GLOBUS_SUCCESS) cast to a OM_uint32 pointer. If an erro has occurred, the resulting error (from calling globus_error_get on this variable) needs to be freed by the caller
context_handle	The imported context
token_status	Errors that occurred while reading from the file
fdp	the file descriptor pointing to a file containing the security context
fperr	FILE * to write error messages

Returns

the major status

3.2.3.13 OM_uint32 globus_gss_assist_init_sec_context (OM_uint32 * *minor_status,* const gss_cred_id_t *cred_handle,* gss_ctx_id_t * *context_handle,* char * *target_name_char,* OM_uint32 *req_flags,* OM_uint32 * *ret_flags,* int * *token_status,* int(*)(void *, void **, size_t *) *gss_assist_get_token,* void * *gss_assist_get_context,* int(*)(void *, void *, size_t) *gss_assist_send_token,* void * *gss_assist_send_context*)

Initialize a gssapi security connection.

Used by the client. The context_handle is returned, and there is one for each connection. This routine will take cake of the looping and token processing, using the supplied get_token and send_token routines.

Parameters

minor_status	GSSAPI return code. The new minor_status is a globus_result_t cast to an OM_uint32. If the call was successful, the minor status is equivalant to GLOBUS_SUCCESS. Otherwise, it is a globus error object ID that can be passed to globus_error_get to get the error object. The error object needs to be freed with globus_object_free.
cred_handle	the cred handle obtained by acquire_cred.
context_handle	pointer to returned context.
target_name_char	char string repersentation of the server to be contacted.
req_flags	request flags, such as GSS_C_DELEG_FLAG for delegation and the GSS_C_MUTUAL_FLAG for mutual authentication.
ret_flags	Pointer to which services are available after the connection is established. Maybe NULL if not wanted.

The Follwing are particular to this assist routine:

Parameters

token_status	the assist routine's get/send token status
gss_assist_get_token	function pointer for getting the token
gss_assist_get_context	first argument passed to the gss_assist_get_token function
gss_assist_send_token	function pointer for setting the token
gss_assist_send_context	first argument passed to the gss_assist_set_token function pointer

Returns

The major status

3.2.3.14 OM_uint32 globus_gss_assist_init_sec_context_async (OM_uint32 * *minor_status,* const gss_cred_id_t *cred_handle,* gss_ctx_id_t * *context_handle,* char * *target_name_char,* OM_uint32 *req_flags,* OM_uint32 * *ret_flags,* void * *input_buffer,* size_t *input_buffer_len,* void ** *output_bufferp,* size_t * *output_buffer_lenp*)

This is a asynchronous version of the **globus_gss_assist_init_sec_context()** (p. 11) function.

Instead of looping itself it passes in and out the read and written buffers and the calling application is responsible for doing the I/O directly.

Parameters

minor_status	GSSAPI return code. The new minor status is a globus_result_t cast to a OM_uint32. If an error occurred (GSS_ERROR(major_status)) the minor_status is a globus error object id. The error object can be obtained via globus_error_get and should be destroyed with globus_object_free when no longer needed. If no error occurred, the minor status is equal to GLOBUS_SUCCESS.
cred_handle	the cred handle obtained by acquire_cred.
context_handle	pointer to returned context.
target_name_char	char string repersentation of the server to be contacted.
req_flags	request flags, such as GSS_C_DELEG_FLAG for delegation and the GSS_C_MUTUAL_FLAG for mutual authentication.
ret_flags	Pointer to which services are available after the connection is established. Maybe NULL if not wanted.
input_buffer	pointer to a buffer received from peer. Should be NULL on first call.
input_buffer_len	length of the buffer input_buffer. Should be zero on first call.
output_bufferp	pointer to a pointer which will be filled in with a pointer to a allocated block of memory. If non-NULL the contents of this block should be written to the peer where they will be fed into the gss_assist_init_sec_context_async() function.
output_buffer_lenp	pointer to an integer which will be filled in with the length of the allocated output buffer pointed to by ∗output_bufferp.

Returns

GSS_S_COMPLETE on successful completion when this function does not need to be called again.

GSS_S_CONTINUE_NEEDED when ∗output_bufferp should be sent to the peer and a new input_buffer read and this function called again.

Other gss errors on failure.

3.2.3.15 OM_uint32 globus_gss_assist_will_handle_restrictions (OM_uint32 ∗ *minor_status,* gss_ctx_id_t ∗ *context_handle*)

Sets the context to handle restrictions.

Parameters

minor_status	the resulting minor status from setting the context handle
context_handle	the context handle to set the minor status of

Returns

the major status from setting the context

3.2.3.16 OM_uint32 globus_gss_assist_get_unwrap (OM_uint32 ∗ *minor_status,* const gss_ctx_id_t *context_handle,* char ∗∗ *data,* size_t ∗ *length,* int ∗ *token_status,* int(∗)(void ∗, void ∗∗, size_t ∗) *gss_assist_get_token,* void ∗ *gss_assist_get_context,* FILE ∗ *fperr*)

Gets a token using the specific tokenizing functions, and performs the GSS unwrap of that token.

See also

gss_unwrap

Parameters

minor_status	GSSAPI return code,

See also

gss_unwrap

Parameters

context_handle	the context
data	pointer to be set to the unwrapped application data. This must be freed by the caller.
length	pointer to be set to the length of the *data* byte array.
token_status	assist routine get/send token status
gss_assist_get_token	a detokenizing routine
gss_assist_get_context	first arg for above routine
fperr	error stream to print to

Returns

GSS_S_COMPLETE on sucess Other gss errors on failure.

3.2.3.17 OM_uint32 globus_gss_assist_wrap_send (OM_uint32 * *minor_status,* const gss_ctx_id_t *context_handle,* char * *data,* size_t *length,* int * *token_status,* int(*)(void *, void *, size_t) *gss_assist_send_token,* void * *gss_assist_send_context,* FILE * *fperr*)

Parameters

minor_status	GSSAPI return code. If the call was successful, the minor status is equal to GLOBUS_SUCCESS. Otherwise, it is an error object ID for which globus_error_get() and globus_object_free() can be used to get and destroy it.
context_handle	the context.
data	pointer to application data to wrap and send
length	length of the *data* array
token_status	assist routine get/send token status
gss_assist_send_token	a send_token routine
gss_assist_send_context	first arg for the send_token
fperr	file handle to write error message to.

Returns

GSS_S_COMPLETE on sucess Other gss errors on failure.

See also

gss_wrap()

3.3 GSI GSS Assist Constants

Enumerations

- enum **globus_gsi_gss_assist_error_t** {
  GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS = 0,
  GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS = 1,
  GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH = 2,
  GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY = 3,

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP = 4,
GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT = 5,
GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO = 6,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT = 7,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP = 8,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN = 9,
GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT = 10,
GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT = 11,
GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE = 12,
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG = 13,
GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR = 14,
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR = 15,
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED = 16,
GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL = 17,
GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME = 18 }

3.3.1 Enumeration Type Documentation

3.3.1.1 enum globus_gsi_gss_assist_error_t

GSI GSS Assist Error codes.

Enumerator:

GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS Success.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS No user entry in gridmap file.

GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_MATCH Error user ID doesn't match.

GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_NO_USER_ENTRY Error with arguments passed to function.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP Error querying gridmap file.

GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_FORMAT Invalid gridmap file format.

GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO System Error.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT Error during context initialization.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP Error during message wrap.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN Error with token.

GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_CONTEXT Error exporting context.

GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT Error importing context.

GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_CALLOUT_HANDLE Error initializing callout handle.

GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_CONFIG Error reading callout configuration.

GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR Error invoking callout.

GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR A GSSAPI returned an error.

GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED Gridmap lookup failure.

GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL Caller provided insufficient buffer space for local identity.

GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_HOSTNAME Failed to obtain canonical host name.

3.4 Security Token Transport

Token routines using fread and fwrite.

Token Get File Descriptor

- int **globus_gss_assist_token_get_fd** (void *arg, void **bufp, size_t *sizep)

Token Send File Descriptor

- int **globus_gss_assist_token_send_fd** (void *arg, void *buf, size_t size)

Token Send File Descriptor Without Length

- int **globus_gss_assist_token_send_fd_without_length** (void *arg, void *buf, size_t size)

Token Send File Descriptor Flag EX

- int **globus_gss_assist_token_send_fd_ex** (void *exp, void *buf, size_t size)

3.4.1 Detailed Description

Token routines using fread and fwrite. Additional code has been added to detect tokens which are sent without a length field. These can currently be only SSL tokens. This does require some knowledge of the underlying GSSAPI, by the application, but is within the guidelines of the GSSAPI specifications.

The get routine will automaticly attempt this test, while a new send routine will check a flag. The old send routine will work as before, sending a 4-byte length.

3.4.2 Function Documentation

3.4.2.1 int globus_gss_assist_token_get_fd (void * *arg*, void ** *bufp*, size_t * *sizep*)

Use a open file discriptor to get a token.

This function provides parameter types that allow it to be passed to **globus_gss_assist_init_sec_context** (p. 11) and **globus_gss_assist_accept_sec_context** (p. 5)

Parameters

arg	the FILE * stream cast to a void pointer
bufp	the resulting token
sizep	the size (number of bytes) read into bufp

Returns

0 on success > 0 is internal return < 0 is the -errno

3.4.2.2 int globus_gss_assist_token_send_fd (void * *arg*, void * *buf*, size_t *size*)

Write a token to the open file descriptor.

WIll write it with a 4 byte length. This function provides parameter types that allow it to be passed to **globus_gss_assist_init_sec_context** (p. 11) and **globus_gss_assist_accept_sec_context** (p. 5)

Parameters

arg	the FILE * stream to send the token on
buf	the token
size	the size of the token in bytes

Returns

0 on success >0 on error <0 on errno error

3.4.2.3 int globus_gss_assist_token_send_fd_without_length (void * *arg*, void * *buf*, size_t *size*)

Write a token to the open file descripter.

Will write it without a length. so as to

3.4.2.4 int globus_gss_assist_token_send_fd_ex (void * *exp*, void * *buf*, size_t *size*)

Write a token to the open file descripter.

will look at the flag to determine if the length field need to be written.

Parameters

exp	the globus_gss_assist_ex variable that holds the FILE * stream and flags to bet set
buf	the token buffer to send
size	size of the token buffer

Returns

0 on success >0 on error <0 on errno error (-errno)

Index

Activation, 1
    GLOBUS_GSI_GSS_ASSIST_MODULE, 2
GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_-
        HOSTNAME
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_-
        CONTEXT
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_CONTEXT
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_-
        NO_USER_ENTRY
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_-
        CALLOUT_HANDLE
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_GRIDMAP_-
        FORMAT
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS
    GSI GSS Assist Constants, 14
globus_gsi_gss_assist_error_t
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_DOESNT_-
        MATCH
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_-
        CONFIG
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_FAILED
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR
    GSI GSS Assist Constants, 14
GLOBUS_GSI_GSS_ASSIST_MODULE
    Activation, 2
globus_gss_assist_accept_sec_context
    Utility Functions, 4
globus_gss_assist_accept_sec_context_async
    Utility Functions, 5
globus_gss_assist_acquire_cred
    Utility Functions, 5
globus_gss_assist_acquire_cred_ext
    Utility Functions, 6
globus_gss_assist_display_status
    Utility Functions, 6
globus_gss_assist_display_status_str
    Utility Functions, 6
globus_gss_assist_get_unwrap
    Utility Functions, 12
globus_gss_assist_gridmap
    Utility Functions, 7
globus_gss_assist_import_sec_context
    Utility Functions, 10
globus_gss_assist_init_sec_context
    Utility Functions, 10
globus_gss_assist_init_sec_context_async
    Utility Functions, 11
globus_gss_assist_lookup_all_globusid
    Utility Functions, 8
globus_gss_assist_map_and_authorize
    Utility Functions, 9
globus_gss_assist_map_local_user
    Utility Functions, 8
globus_gss_assist_token_get_fd
    Security Token Transport, 15
globus_gss_assist_token_send_fd
    Security Token Transport, 15
globus_gss_assist_token_send_fd_ex
    Security Token Transport, 15
globus_gss_assist_token_send_fd_without_length
    Security Token Transport, 15
globus_gss_assist_userok
    Utility Functions, 7
globus_gss_assist_will_handle_restrictions
    Utility Functions, 12
globus_gss_assist_wrap_send
    Utility Functions, 12
GlobusGssAssistFreeDNArray
    Utility Functions, 4
GSI GSS Assist Constants, 13
    GLOBUS_GSI_GSS_ASSIST_BUFFER_TOO_SMALL,
        14
    GLOBUS_GSI_GSS_ASSIST_CALLOUT_ERROR,
        14
    GLOBUS_GSI_GSS_ASSIST_ERROR_CANONICALIZING_-
        HOSTNAME, 14
    GLOBUS_GSI_GSS_ASSIST_ERROR_ERRNO, 14
    GLOBUS_GSI_GSS_ASSIST_ERROR_EXPORTING_-

CONTEXT, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_IMPORTING_-CONTEXT, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_IN_GRIDMAP_-NO_USER_ENTRY, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_INITIALIZING_-CALLOUT_HANDLE, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_INVALID_-GRIDMAP_FORMAT, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_SUCCESS, 14
globus_gsi_gss_assist_error_t, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_USER_ID_-DOESNT_MATCH, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_ARGUMENTS, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_CALLOUT_-CONFIG, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_GRIDMAP, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_INIT, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_TOKEN, 14
GLOBUS_GSI_GSS_ASSIST_ERROR_WITH_WRAP, 14
GLOBUS_GSI_GSS_ASSIST_GRIDMAP_LOOKUP_-FAILED, 14
GLOBUS_GSI_GSS_ASSIST_GSSAPI_ERROR, 14
globus_gss_assist_will_handle_restrictions, 12
globus_gss_assist_wrap_send, 12
GlobusGssAssistFreeDNArray, 4
NI_MAXHOST, 4

NI_MAXHOST
Utility Functions, 4

Security Token Transport, 14
globus_gss_assist_token_get_fd, 15
globus_gss_assist_token_send_fd, 15
globus_gss_assist_token_send_fd_ex, 15
globus_gss_assist_token_send_fd_without_length, 15

Utility Functions, 2
globus_gss_assist_accept_sec_context, 4
globus_gss_assist_accept_sec_context_async, 5
globus_gss_assist_acquire_cred, 5
globus_gss_assist_acquire_cred_ext, 6
globus_gss_assist_display_status, 6
globus_gss_assist_display_status_str, 6
globus_gss_assist_get_unwrap, 12
globus_gss_assist_gridmap, 7
globus_gss_assist_import_sec_context, 10
globus_gss_assist_init_sec_context, 10
globus_gss_assist_init_sec_context_async, 11
globus_gss_assist_lookup_all_globusid, 8
globus_gss_assist_map_and_authorize, 9
globus_gss_assist_map_local_user, 8
globus_gss_assist_userok, 7