globus callout

2.2

Generated by Doxygen 1.8.0

Thu May 3 2012 09:42:46

Contents

1 Globus Callout API **1**

2 Module Index **2**

2.1 Modules 2

3 Module Documentation **2**

3.1 Activation 2

3.1.1 Detailed Description 2

3.1.2 Define Documentation 2

3.2 Callout Handle Operations 3

3.2.1 Detailed Description 3

3.2.2 Typedef Documentation 3

3.2.3 Function Documentation 3

3.3 Callout Configuration 4

3.3.1 Detailed Description 4

3.3.2 Function Documentation 4

3.4 Callout Invocation 6

3.4.1 Detailed Description 6

3.4.2 Typedef Documentation 6

3.4.3 Function Documentation 6

3.5 Globus Callout Constants 7

3.5.1 Enumeration Type Documentation 7

1 Globus Callout API

This API is intended to ease integration of configurable callouts into the Globus Toolkit and to provide a platform independent way of dealing with runtime loadable functions. It (hopefully) achieves this goal by providing the following functionality:

- It provides a function for reading callout configuration files. Files are assumed to have the following format:
  - Anything after a '#' is assumed to be a comment
  - Blanks lines are ignored
  - Lines specifying callouts have the format abstract type library symbol where "abstract type" denotes the type of callout, e.g. globus_gram_jobmanager_authz, "library" denotes the library the callout can be found in and "symbol" denotes the function name of the callout.

It provides a API function for registering callouts

- All callouts are assumed to have the function signature globus_result_t callout_func(va_list ap)
- It provides a function for calling a callout given a abstract type. If multiple callouts are defined for the same abstract type then all callouts for the abstract type will be called. Implementers should not rely on any

correlation between the order of configuration and the order of invocation of callouts of the same abstract type.

Any program that uses Globus Callout functions must include "globus_callout.h".

2 Module Index

2.1 Modules

Here is a list of all modules:

Activation 2

Callout Handle Operations 3

Callout Configuration 4

Callout Invocation 6

Globus Callout Constants 7

3 Module Documentation

3.1 Activation

Defines

- #define **GLOBUS_CALLOUT_MODULE**

3.1.1 Detailed Description

Globus Callout API uses standard Globus module activation and deactivation. Before any Globus Callout API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_CALLOUT_MODULE)
```

This function returns GLOBUS_SUCCESS if Globus Callout API was successfully initialized, and you are therefore allowed to subsequently call Globus Callout API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus Callout API, the following function must be called:

```
globus_module_deactivate(GLOBUS_CALLOUT_MODULE)
```

This function should be called once for each time Globus Callout API was activated.

3.1.2 Define Documentation

3.1.2.1 #define GLOBUS_CALLOUT_MODULE

Module descriptor.

3.2 Callout Handle Operations

Typedefs

- typedef struct
  globus_i_callout_handle_s * **globus_callout_handle_t**

Initialize Handle

- globus_result_t **globus_callout_handle_init** (**globus_callout_handle_t** *handle)

Destroy Handle

- globus_result_t **globus_callout_handle_destroy** (**globus_callout_handle_t** handle)

3.2.1 Detailed Description

Initialize and Destory a Globus Callout Handle structure. This section defines operations for initializing and destroying Globus Callout Handle structure.

3.2.2 Typedef Documentation

3.2.2.1 typedef struct globus_i_callout_handle_s* globus_callout_handle_t

Callout handle type definition.

3.2.3 Function Documentation

3.2.3.1 globus_result_t globus_callout_handle_init (globus_callout_handle_t * *handle*)

Initialize a Globus Callout Handle.

Parameters

handle	Pointer to the handle that is to be initialized

Returns

GLOBUS_SUCCESS if successful A Globus error object on failure: GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE

3.2.3.2 globus_result_t globus_callout_handle_destroy (globus_callout_handle_t *handle*)

Destroy a Globus Callout Handle.

Parameters

handle	The handle that is to be destroyed

Returns

GLOBUS_SUCCESS

3.3 Callout Configuration

Configure Callouts

- globus_result_t **globus_callout_read_config** (**globus_callout_handle_t** handle, char *filename)
- globus_result_t **globus_callout_register** (**globus_callout_handle_t** handle, char *type, char *library, char *symbol)

3.3.1 Detailed Description

Functions for registering callouts. This section defines operations for registering callouts. Callouts may be registered either through a configuration file or through calls to globus_callout_register.

3.3.2 Function Documentation

3.3.2.1 globus_result_t globus_callout_read_config (globus_callout_handle_t *handle,* char * *filename*)

Read callout configuration from file.

This function read a configuration file with the following format:

- Anything after a '#' is assumed to be a comment
- Blanks lines are ignored
- Lines specifying callouts have the format abstract type library symbol where "abstract type" denotes the type of callout, e.g. globus_gram_jobmanager_authz, "library" denotes the library the callout can be found in and "symbol" denotes the function name of the callout. The library argument can be specified in two forms, libfoo or libfoo_<flavor>. When using the former version the current flavor will automatically be added to the library name.

Parameters

handle	The handle that is to be configured
filename	The file to read configuration from

Returns

GLOBUS_SUCCESS A Globus error object on failure: GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY

3.3.2.2 globus_result_t globus_callout_register (globus_callout_handle_t *handle,* char * *type,* char * *library,* char * *symbol*)

Register callout configuration

This function registers a callout type in the given handle.

Parameters

handle	The handle that is to be configured
type	The abstract type of the callout
library	The location of the library containing the callout
symbol	The symbol (ie function name) for the callout

Returns

GLOBUS_SUCCESS A Globus error object on failure: GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY

3.4 Callout Invocation

Typedefs

- typedef globus_result_t(∗ **globus_callout_function_t**)(va_list ap)

Invoking Callouts

- globus_result_t **globus_callout_call_type** (**globus_callout_handle_t** handle, char ∗type,...)

3.4.1 Detailed Description

Functions for invoking callouts. This section defines a operation for invoking callouts by their abstract type.

3.4.2 Typedef Documentation

3.4.2.1 typedef globus_result_t(∗ globus_callout_function_t)(va_list ap)

Callout function type definition.

3.4.3 Function Documentation

3.4.3.1 globus_result_t globus_callout_call_type (globus_callout_handle_t *handle,* char ∗ *type, ...*)

Call a callout of specified abstract type

This function looks up the callouts corresponding to the given type and invokes them with the passed arguments.

If a invoked callout returns an error it will be chained to a error of the type GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR and no more callouts will be called.

Parameters

handle	A configured callout handle
type	The abstract type of the callout that is to be invoked

Returns

GLOBUS_SUCCESS A Globus error object on failure: GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR GLOBUS_CALLOUT_ERROR_WITH_DL GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY

3.5 Globus Callout Constants

Enumerations

- enum **globus_callout_error_t** {
  GLOBUS_CALLOUT_ERROR_SUCCESS = 0,
  GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE = 1,
  GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE = 2,
  GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE = 3,
  GLOBUS_CALLOUT_ERROR_WITH_DL = 4,
  GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY = 5,
  GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED = 6,
  GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR = 7,
  GLOBUS_CALLOUT_ERROR_LAST = 8 }

3.5.1 Enumeration Type Documentation

3.5.1.1 enum globus_callout_error_t

Globus Callout Error codes.

Enumerator:

GLOBUS_CALLOUT_ERROR_SUCCESS Success - never used.

GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE Hash table operation failed.

GLOBUS_CALLOUT_ERROR_OPENING_CONF_FILE Failed to open configuration file.

GLOBUS_CALLOUT_ERROR_PARSING_CONF_FILE Failed to parse configuration file.

GLOBUS_CALLOUT_ERROR_WITH_DL Dynamic library operation failed.

GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY Out of memory.

GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGISTERED The abstract type could not be found.

GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR The callout itself returned a error.

GLOBUS_CALLOUT_ERROR_LAST Last marker - never used.

Index

Activation, 1
    GLOBUS_CALLOUT_MODULE, 2

Callout Configuration, 4
    globus_callout_read_config, 4
    globus_callout_register, 4
Callout Handle Operations, 3
    globus_callout_handle_destroy, 3
    globus_callout_handle_init, 3
    globus_callout_handle_t, 3
Callout Invocation, 6
    globus_callout_call_type, 6
    globus_callout_function_t, 6

GLOBUS_CALLOUT_ERROR_CALLOUT_ERROR
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_LAST
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_OPENING_CONF_FIL-
    E
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_OUT_OF_MEMORY
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_PARSING_CONF_FIL-
    E
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_SUCCESS
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_TYPE_NOT_REGIST-
    ERED
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_WITH_DL
    Globus Callout Constants, 7
GLOBUS_CALLOUT_ERROR_WITH_HASHTABLE
    Globus Callout Constants, 7
GLOBUS_CALLOUT_MODULE
    Activation, 2
Globus Callout Constants, 7
    GLOBUS_CALLOUT_ERROR_CALLOUT_ERR-
    OR, 7
    GLOBUS_CALLOUT_ERROR_LAST, 7
    GLOBUS_CALLOUT_ERROR_OPENING_CON-
    F_FILE, 7
    GLOBUS_CALLOUT_ERROR_OUT_OF_MEMO-
    RY, 7
    GLOBUS_CALLOUT_ERROR_PARSING_CONF-
    _FILE, 7
    GLOBUS_CALLOUT_ERROR_SUCCESS, 7
    GLOBUS_CALLOUT_ERROR_TYPE_NOT_RE-
    GISTERED, 7
    GLOBUS_CALLOUT_ERROR_WITH_DL, 7
    GLOBUS_CALLOUT_ERROR_WITH_HASHTAB-
    LE, 7
    globus_callout_error_t, 7
globus_callout_call_type
    Callout Invocation, 6
globus_callout_error_t
    Globus Callout Constants, 7
globus_callout_function_t
    Callout Invocation, 6
globus_callout_handle_destroy
    Callout Handle Operations, 3
globus_callout_handle_init
    Callout Handle Operations, 3
globus_callout_handle_t
    Callout Handle Operations, 3
globus_callout_read_config
    Callout Configuration, 4
globus_callout_register
    Callout Configuration, 4